Hands-on tutorials

Launch and Configure a WordPress Instance with Amazon Lightsail



Launch and Configure a WordPress Instance with Amazon Lightsail: Hands-on tutorials

Copyright © 2025 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Table of Contents

Launch and Configure a WordPress Instance with Amazon Lightsail i		
	Overview	1
	Implementation	1
	Congratulations	21

Launch and Configure a WordPress Instance with Amazon Lightsail

AWS experience	Beginner
Time to complete	10 minutes
Cost to complete	<u>Free Tier</u> eligible
Last updated	August 4, 2022

Overview

Amazon Lightsail is one of the easiest ways to get started with AWS. It offers virtual servers, storage, databases, and networking, plus a cost-effective, monthly plan.

This tutorial shows you how to launch and configure a WordPress instance on Lightsail. It includes steps to connect to your instance by using SSH, sign in to your WordPress website, create a static IP and attach it to your instance, create a DNS zone, and map it to your instance.

When you're done with this tutorial, you will have the fundamentals to get your WordPress website up and running on Amazon Lightsail.

Get started with Lightsail for free.

Implementation

Step 1: Create a WordPress instance in Lightsail

Complete the following steps to get your WordPress instance up and running on Lightsail.



Note

For more information about creating an instance in Lightsail, see Create an Amazon Lightsail instance in the Lightsail documentation.

Overview

1. Create an Amazon Lightsail account

This tutorial is free tier eligible.


Sign up for AWS

Already have an account? Sign-in

2. Create a Lightsail instance


Sign in to the Lightsail console.

On the Instances tab of the Lightsail home page, choose **Create instance**.



3. Select a Region


An AWS Region and Availability Zone is selected for you. Choose **Change AWS Region and Availability Zone** if you want to create your instance in another location.



4. Choose an image

Choose your instance image.


- Choose **Linux/Unix** as the platform.
- Choose WordPress as the blueprint.



5. Select an instance plan

Choose an instance plan.

A plan includes a machine configuration (RAM, SSD, vCPU) at a low, predictable cost, and data transfer allowance. You can try the \$3.50 USD Lightsail plan without charge for three months (up to 750 hours). AWS credits the first three months to your account.




6. Create your instance

Enter a name for your instance and choose **Create instance**.

Resource name guidelines:

- Must be unique within each AWS Region in your Lightsail account.
- Must contain 2 to 255 characters.
- Must start and end with an alphanumeric character or number.
- Can include alphanumeric characters, numbers, periods, dashes, and underscores.



Step 2: Connect to your instance via SSH and get the password for your WordPress website

The default password to sign in to the administration dashboard of your WordPress website is stored on the instance.


Complete the following steps to connect to your instance using the browser-based SSH client in the Lightsail console, and get the password for the administration dashboard.

Note

For more information, see Obtain the default application username and password for Lightsail Bitnami.

Connect using SSH

On the **Instances** tab of the <u>Lightsail home page</u>, choose the SSH quick-connect icon for your WordPress instance.



2. Retrieve the password

After the browser-based SSH client window opens, enter the following command to retrieve the default application password:

cat \$HOME/bitnami_application_password

3. Note the password

Make note of the password displayed on the screen. You use it later to sign in to the administration dashboard of your WordPress website.

Step 3: Sign in to the administration dashboard of your WordPress website

Now that you have the password for the administration dashboard of your WordPress website, you can sign in. In the administration dashboard, you can change your user password, install plugins, change the theme of your website, and more.


Complete the following steps to sign in to the administration dashboard of your WordPress website.

Log in to WordPress

In a browser, go to:

```
http://PublicIpAddress/wp-login.php
```

In the address, replace **PublicIpAddress** with the public IP address of your WordPress instance. You can get your instance's public IP address from the Lightsail console as shown in the image at the right.



2. Enter your credentials


Log in to your instance.

- In the Username or Email Address box, enter user.
- In the **Password** box, enter the default password obtained earlier in this tutorial.
- Choose Log in.



3. Manage WordPress

You are now signed in to the administration dashboard of your WordPress website where you can perform administrative actions. For more information about administering your WordPress website, see the WordPress Codex in the WordPress documentation.



Step 4: Create a Lightsail static IP address and attach it to your WordPress instance

The default public IP for your WordPress instance changes if you stop and start your instance. A static IP address, attached to an instance, stays the same even if you stop and start your instance.


Complete the following steps to create a static IP address and attach it to your WordPress instance.



For more information, see <u>Create a static IP and attach it to an instance in Amazon</u> Lightsail.


1. Choose your instance

On the Instances tab of the Lightsail home page, choose your running WordPress instance.




Create a static IP

Choose the Networking tab, then choose Create static IP.




3. Attach to an instance

The static IP location is preselected based on the instance zone that you chose earlier. Select the created WordPress instance from the **Attach to an instance** dropdown.



4. Name your static IP

Name your static IP, then choose Create.



Step 5: Create a Lightsail DNS zone and map a domain to your WordPress instance

Transfer management of your domain's DNS records to Lightsail. This allows you to more easily map a domain to your WordPress instance, and manage more of your website's resources using the Lightsail console.


Complete the following steps to create a Lightsail DNS zone and map a domain to your WordPress instance.



For more information, see <u>Creating a DNS zone to manage your domain's DNS records in</u> Amazon Lightsail.


1. Create a DNS zone

On the Networking tab of the Lightsail home page, choose Create DNS zone.



2. Add your domain


Enter your domain, then choose Create DNS zone.



3. Note the name servers

Make note of the name server address listed on the page.

You add these name server addresses to your domain name's registrar to transfer management of your domain's DNS records to Lightsail.




Add an A record

After management of your domain's DNS records are transferred to Lightsail, add an A record to point the apex of your domain to your WordPress instance, as follows:

You add these name server addresses to your domain name's registrar to transfer management of your domain's DNS records to Lightsail.

In the DNS zone for your domain, choose Add record.




5. Configure DNS settings

Continue adding the following details to complete pointing the apex of your domain to your WordPress instance:

- a. In the **Subdomain** box, enter an @ symbol to map the apex of your domain (such as example.com) to your instance. The @ symbol explicitly symbolizes that you're adding an apex record. It is not added as a subdomain.
- b. In the **Resolves to** box, choose the static IP that you attached to the WordPress instance in the previous step of this tutorial.
- c. Choose the green **save** icon.


Allow time for the change to propagate through the internet's DNS before your domain begins routing traffic to your WordPress instance.



Clean up resources


1. Delete instance

On the **Instances** tab of the <u>Lightsail home page</u>, choose the ellipsis (:) icon next to the WordPress instance you just created and choose **Delete**.



2. Confirm deletion

Choose Yes, delete from the prompt.



Congratulations

Congratulations! You have used Amazon Lightsail to launch and deploy a WordPress instance.

Amazon Lightsail is a great choice to develop, build, and deploy a variety of applications like WordPress, websites, and blog platforms.

Congratulations 21